

SHRINE 4.0.0 Chapter 8 - SHRINE's Configuration File

SHRINE gets its configuration from a configuration file named **shrine.conf** in `/opt/shrine/tomcat/lib`. If you are installing a downstream (non-hub) node, copy the `shrine-setup/qep-and-adapter-shrine.conf` file from `shrine-setup.zip` to tomcat's lib directory.

```
cp shrine-setup/qep-and-adapter-shrine.conf /opt/shrine/tomcat/lib/shrine.conf
```

If you are creating a hub use `hub-and-qep-shrine.conf` - and skip to [SHRINE 4.0.0 Chapter 8.2 - Configuring a Hub](#).

In this guide, we will refer to this file often and will go more in detail on configuring this file in the later chapters). Here is the example `shrine.conf` file from `shrine-setup.zip`. You will need to customize it for your own node on your network. In the example below, the first four lines in the shrine section define values for parameters that are used throughout the configuration file.

shrine.conf

```
shrine {  
  
    shrineHubBaseUrl = "https://shrine-hub.faraway.com:6443" //The shrine hub's URL as observed from this tomcat  
server  
    i2b2BaseUrl = "http://i2b2.example.com:9090" //The local i2b2's URL as observed from this tomcat server  
    i2b2Domain = "exampleDomain"  
    i2b2ShrineProjectName = "SHRINE"  
  
    nodeKey = "testNode" //node key to get information from the hub about this node.  
  
    //shrineDatabaseType = "mysql" // "mysql" by default. It can be "sqlserver" "mysql" or "oracle"  
  
    webclient {  
        siteAdminEmail = "shrine-admin@example.com"  
    }  
  
    hiveCredentials {  
        username = "demo"  
        crcProjectId = "Demo"  
    }//hiveCredentials  
  
    steward {  
        emailDataSteward {  
            //provide the email address of the shrine node system admin, to handle bounces and invalid addresses  
            from = "shrine-admin@example.com"  
            //provide the email address of the shrine node system admin, to handle bounces and invalid addresses  
            to = "shrine-steward@example.com"  
            //provide the externally-reachable URL for the data steward  
            externalStewardBaseUrl = "https://shrine.example.com:6443/shrine-api/shrine-steward"  
        }  
    }//steward  
}//shrine
```

(Optional) To require users to be a member of a specific PM cell project, add the following to `shrine.conf`:

```
shrine.authenticate.pmProjectName = "<enter PM cell project name here>"
```

All passwords are stored in `password.conf` file in `/opt/shrine/tomcat/lib` instead of `shrine.conf`.

password.conf

```
shrine.hiveCredentials.password = "changeit"
```

**nodeKey parameter**

The nodeKey value will be used to identify your node from the Hub. This value must be a unique alphanumeric identifier in your network. If you have any questions, please contact the hub administrator for more information.

**i2b2Domain parameter**

Choose a custom value for your domain parameter that clearly identifies your institution. Do not leave it at its default values.